

Oxygen Engine Handbook

Contents

Hotkeys.....	3	Basics.....	14
Window Mode.....	3	String Access / Manipulation.....	15
Rendering.....	3	Flag Registers.....	16
Simulation Time Control.....	3	Stack Access.....	16
Audio Volume.....	4	Memory Data Processing.....	17
Game Resolution.....	4	Persistent Data Access.....	17
Miscellaneous functions on the F keys.....	4	Raw Data Loading.....	18
Save States.....	5	Game Resolution.....	19
Performance.....	5	Input.....	20
Memory View.....	5	Miscellaneous.....	20
Side Panel.....	5	Debugging.....	20
Debug Keys.....	5	Control Flow.....	22
Built-in Debugging Tools.....	6	Direct VRAM Access.....	22
Memory View.....	6	Emulated VDP (Video Display Processor).....	23
Side Panel.....	6	Oxygen Renderer.....	26
Lemon Script.....	8	Audio Playback.....	32
About the Lemon Script Language.....	8	Misc Functions.....	33
Language Details.....	9	Undocumented.....	34
Preprocessor Definitions.....	13	Rendering.....	35
Engine Script Functions.....	14	Render Queues Overview.....	35
		Palette vs. Component Sprites.....	35

HOTKEYS

Window Mode

- Alt + Enter = Toggle fullscreen / window mode
- Esc = Toggle fullscreen / window mode (same as above)
- Shift + Esc = Set window size to game resolution

Rendering

- Alt + F = Previous filtering method
- Alt + G = Next filtering method
- Alt + B = Change background blur setting
- Alt + 1 ... Alt + 8 = Toggle rendering of layer:
 - Alt + 1 = Plane B, no priority
 - Alt + 2 = Plane A, no priority
 - Alt + 3 = VDP sprites, no priority
 - Alt + 4 = Custom sprites, no priority
 - Alt + 5 = Plane B, with priority
 - Alt + 6 = Plane A, with priority
 - Alt + 7 = VDP sprites, with priority
 - Alt + 8 = Custom sprites, with priority
 - Note that certain rendered objects like custom planes and debug draws can't be toggled

Simulation Time Control

The following hotkeys control the simulation speed:

- Numpad 1 = Normal game speed
- Numpad 2 = Fast-forward 3x game speed (with Ctrl: 2x game speed)
- Numpad 3 = Fast-forward 5x game speed
- Numpad 4 = Fast-forward 10x game speed
- Numpad 7 = Fast-forward at maximum speed
- Numpad 5 = Slowmotion 0.2x game speed (with Ctrl: 0.5x game speed)
- Numpad 6 = Slowmotion 0.05x game speed (with Ctrl: 0.01x game speed)
- Numpad 0 = Pause simulation
- Numpad Period = Single-frame step
- Shift + Numpad Period = Continue at normal speed until the next watch triggers or something gets logged

Audio Volume

Increase or reduce the global audio volume:

- Numpad Plus = Increase global volume
- Numpad Minus = Reduce global volume

Game Resolution

Change the horizontal game resolution:

- Numpad Divide = Reduce width
- Numpad Multiply = Increase width

Miscellaneous functions on the F keys

- F1 = Open the config.json file
- F2 = Write a game recording file
- F3 = Rescan for connected controllers
- F4 = Switch controls for player 1 and player 2

Save States

- F5 = Go to the Save State menu
- F8 = Go to the Load State menu
- F7 = Quick load last loaded state

Performance

- Alt + P = Switch between performance displays
 - Warning: Don't leave the first one (with the flickering box) on for a longer period of time - like more than some minutes -, as it isn't too healthy for some LCD screens

Memory View

Keys I, O and L control the Memory View, see section on this Tool.

Side Panel

Keys Home and End control which Side Panel tab is shown.

Debug Keys

Numbers 1, 2 ..., 9 and 0 on the main keyboard can be read as Debug Keys by the scripts, see script binding "Key0".
E.g. for Sonic 3 A.I.R., key 1 disables camera bounds, and key 0 toggles a debug output for certain collision boxes.

BUILT-IN DEBUGGING TOOLS

Memory View

The Memory View is a simple output of a part of memory. It allows you to investigate both ROM and RAM data, as well as the extended RAM. The data is shown in hexadecimal form, like in a hex editor. The leftmost text in each line is the address of the first byte shown.

Use the following keys:

- **I** = Show the Memory View, change number of lines shown, and hide it again
- **O / L** = Navigate through memory by changing the start address from where data is shown; O = up, L = down
 - Change by 0x20 if no other key is pressed
 - With Shift: Change by 0x100
 - With Ctrl: Change by 0x1000
 - With Shift + Ctrl: Change by 0x10000

Side Panel

The Side Panel displays various types of debug information arranged in several tabs:

- **C = Call Frames**
Lists all functions called in the last simulated frame.
- **U = Unknown Addresses**
In case simulation encountered jumps or calls to unknown addresses, these are listed here.
- **W = Watches**
Here you can find the active memory watches, with a white highlight on all that triggered last frame.
Click on a single change to get a call stack for it.
- **G = Global Defines**
Shows all script defines with a fixed memory address, i.e. all global variables in memory.
You can investigate on their values and set watches on them here as well.

- **R = Rendered Geometry**

Gives an overview over all planes, sprites, etc. that was rendered in the last frame.

In most (but not all) cases, hovering your mouse over an entry highlights its bounding box in the viewport.

- **V = VRAM Writes**

This is some kind of persistent watch for video memory. Lists all writes to VRAM that got triggered by the scripts.

- **L = Log**

In addition to the usual log output on screen, all logged events are displayed here again.

But this time with the option to click on it and get a call stack.

LEMON SCRIPT

About the Lemon Script Language

Lemon script is a homebrew scripting language originally designed to be an alternative representation of M68K assembler code.

As such it is a quite simple language, only including features that were necessary for porting Sonic 3 A.I.R.

If you want to engage in scripting, make yourself familiar with the language first. It is somewhat similar in syntax to languages like C (or C++, C#, Java, whatever) - but with some differences, most notably:

1. Line break handling
 - Line breaks are regarded as end of a code line. That implies that you can't split expressions like function calls into multiple lines.
 - For that reason, there's no need to end a line with a semi-colon. Doing so results in a compile error.
 - Curly braces { } always have to be placed in their own lines.
2. There is only a limited number of data types that can be used, and currently no way to define additional data types.
3. Definitions of functions and global variables have to start with keywords `function` and `global`, respectively.

Language Details

Known language bugs & quirks

Things that might behave somewhat unexpectedly:

- Short circuit evaluation for boolean operators `&&` and `||` as known from many other languages is not supported. That means the right side always gets evaluated, even if the result would be already determined by evaluating only the left side.
Example: `if (a != 0 && doStuff(a))` --> the function `doStuff` will be called even if `a == 0`.

Identifiers

Identifiers for variables, functions, defines, etc. consist of the following characters:

`'A'..'Z', 'a'..'z', '0'..'9', '_', '.'`

So unlike other languages, the dot is just a normal part of an identifier with no special meaning.

Lemon script is case-sensitive.

Data Types

There are only a handful of basic data types for variables and constants that can be used:

- `u8` is a 8-bit / 1-byte unsigned integer, values ranging from 0 to 2^8-1 (0 to 255)
- `u16` is a 16-bit / 2-byte unsigned integer, values ranging from 0 to $2^{16}-1$
- `u32` is a 32-bit / 4-byte unsigned integer, values ranging from 0 to $2^{32}-1$
- `u64` is a 64-bit / 8-byte unsigned integer, values ranging from 0 to $2^{64}-1$
- `s8` is a 8-bit / 1-byte signed integer, values ranging from -2^7 to 2^7-1 (-128 to 127)
- `s16` is a 16-bit / 2-byte signed integer, values ranging from -2^{15} to $2^{15}-1$
- `s32` is a 32-bit / 4-byte signed integer, values ranging from -2^{31} to $2^{31}-1$
- `s64` is a 64-bit / 8-byte signed integer, values ranging from -2^{63} to $2^{63}-1$

For boolean values, you can use the type `bool`, but note that this is not an actual data type, instead only a synonym for `u8`. When evaluating a value to an actual bool (e.g. in an if-clause condition), all values $\neq 0$ are regarded as true, and 0 is regarded as false.

There is no floating point data type. Because of M68K code origins.

The `void` type exists, but only as return value type for functions.

Strings are a bit tricky because they don't use a real data type either. Instead, strings are referenced using `u64` variables (or the `string` type, which is only an alias for `u64`). The value stored in there is actually a 64-bit hash of the string.

Use the `stringformat` function to create strings if needed, and also for concatenating two strings - do not use the arithmetic operator `+`, as it will just use the two strings' hash values and produce garbage as a result.

Note that strings are always 8-bits per character, usually interpreted as ASCII.

Memory Access

To access a piece of memory (including ROM and RAM), use a basic data type followed by the address in square brackets. This can be used for both reading and writing data.

Example: `u16[0x012345]` would access the bytes at addresses 0x012345 and 0x012346.

Some notes here:

- Memory access is always little endian, just like the Mega Drive's / Genesis' M68K processor.
- Unlike with the M68K, it's allowed to access odd addresses with all data sizes.
- The address can be constant or calculated at runtime like in `u32[myAddressVariable + 4]`

The total mapped memory space is limited to 24-bit addresses (0x000000 to 0xfffff), memory accesses only use the lower 24-bits. This means that addresses 0xffff1234 and 0xff1234 are identical.

Inside the memory space, not all addresses are valid to access. The following are:

- 0x000000 .. 0x3ffff = ROM -- this is where the game ROM content is stored
- 0x800000 .. 0xfffff = "Shared memory", actually additional RAM

- 0xff0000 .. 0xfffff = RAM – for game ports like Sonic 3 A.I.R., this is mostly used the same way as by the original game

Registers

The registers a0 .. d7 of the M68K are represented in lemon script by the global variables `A0` .. `D7`.

These have some special sub-variables that allow for partial access. Here's an overview using `D0` as example:

- `D0` -> This is the full 32-bit register, interpreted as unsigned by default
- `D0.u8` -> Lowest 8 bits, interpreted as unsigned 8-bit value
- `D0.s8` -> Lowest 8 bits, interpreted as signed 8-bit value
- `D0.u16` -> Lowest 16 bits, interpreted as unsigned 16-bit value
- `D0.s16` -> Lowest 16 bits, interpreted as signed 16-bit value
- `D0.u32` -> Lowest 32 bits, interpreted as unsigned 32-bit value (same as `D0`)
- `D0.s32` -> Lowest 32 bits, interpreted as signed 32-bit value

Functions

Functions always have to start with the "function" keyword. It's allowed to create overloads of the same function, i.e. declare it multiple times with different parameters. When resolving calls, the compiler will choose the most fitting version of the function.

If you're using functions with actual return types (not void), make sure all paths return a value. Otherwise, you won't get a compiler error, but nasty run-time errors...

Address Hooks

Functions can have so-called address hooks. This is an associated ROM address for the function, to allow for indirect calls using addresses with the "call" keyword, like in `call 0x123456 + D0.u16`.

Whenever such a call is executed, the function with the resulting address's hook will get called. Or none at all, if there is no function with that hook, leading to the call having no effect.

Address hooks are declared with a line like this preceding the function header:

```
//# address-hook(0x123456) end(0x123478)
```

Here, the first curved brackets include the address for this function. The "end" part afterwards is optional and has only informative meaning for functions directly representing original M68K code.

Includes

There's usually only a single script file that gets loaded as a starting point, e.g. a "main.lemon" file.

In order to add more script files to compilation, `include` lines like the following examples are used:

<code>include myfunctions</code>	→ includes the contents of a script file named "myfunctions.lemon"
<code>include utils/helpers</code>	→ includes the contents of a single script file "helpers.lemon" in a subdirectory named "utils"
<code>include entities/player/?</code>	→ includes the contents of all script files in a nested subdirectory "entities/player"

The paths used in includes are always relative to the including script file's location.

Note that the wildcard `?` can only be used to include all *.lemon files in a directory, but not for additional filtering or recursive includes of subdirectories.

Preprocessor Definitions

STANDALONE

In ported game scripts like Sonic 3 A.I.R., you might stumble across usage of the `STANDALONE` preprocessor definition. This one is always set to true for S3AIR.

But why does it even exist?

The idea is that when `STANDALONE` is false, the code behaves exactly like the original game code. That means that all changes made to the game are marked with a `#if STANDALONE` block or similar.

(Nitpicking side-note: Most but not *all* changes are marked this way. There are few exceptions like calls to `getScreenWidth()` or `getScreenExtend()` that will return different values in the widescreen standalone than in the original game, where a fixed screen width of 320 and a screen extend of 0 is used.)

GAMEAPP

The `GAMEAPP` preprocessor definition makes the difference between the Oxygen Development Application ("OxygenApp.exe") and the actual game application (like "Sonic3AIR.exe").

In conclusion:

- Game application: `GAMEAPP = 1` `STANDALONE = 1`
- Oxygen dev app: `GAMEAPP = 0` `STANDALONE = 1`

ENGINE SCRIPT FUNCTIONS

Basics

s8 min(s8 a, s8 b)

u8 min(u8 a, u8 b)

s16 min(s16 a, s16 b)

u16 min(u16 a, u16 b)

s32 min(s32 a, s32 b)

u32 min(u32 a, u32 b)

- Returns the smaller value of inputs a and b

s8 max(s8 a, s8 b)

- Returns the larger value of inputs a and b
- Also exists for types u8, s16, u16, s32, u32

s8 clamp(s8 a, s8 b, s8 c)

- Limits the value in a into the range defined by b and c; the result is:
 - b if a <= b
 - c if a >= c
 - a if it's between b and c
- Also exists for types u8, s16, u16, s32, u32

u8 abs(s8 value)

- Returns absolute value of the input, i.e. negates it if it's negative
- Also exists for 16-bit and 32-bit data sizes

u32 sqrt(u32 value)

- Calculates the square root of the input value, rounded down to the next integer value

String Access / Manipulation

u32 strlen(u64 string)

- Returns the length of the stringformat

u8 getchar(u64 string, u32 index)

- Returns the character at the given index

u64 substring(u64 string, u32 index, u32 length)

- Builds a substring, starting at index with the given length

u64 stringformat(u64 format, ...)

- Creates a string by filling in values into a "printf"-like pattern
- The format parameter has to be a string and supports the following placeholders:
 - %d for integer parameter, output as decimal number
 - %x for integer parameter, output as (unsigned) hexadecimal number; note that this will not add any prefix like "0x"

- %02d or %02x for integer output (decimal or hexadecimal, respectively), and an enforced minimum number of digits to be filled up with zeroes; replace the 2 with any other single digit
- This function supports up to 8 additional value parameters

Flag Registers

Note: The internal flag registers of the engine – Zero and Negative Flag – only exist for easier compatibility of scripts with original M68K code. Use the following functions only where needed, and avoid using them in your own new script code.

`bool _equal()`

- Returns true if the Zero Flag is set.

`bool _negative()`

- Returns true if the Negative Flag is set.

`void _setZeroFlagByValue(u32 value)`

- Set the Zero Flag by the given value. It will be set if the input value is exactly zero, and cleared in all other cases.

`void _setNegativeFlagByValue(s8 value)`

`void _setNegativeFlagByValue(s16 value)`

`void _setNegativeFlagByValue(s32 value)`

- Set the Negative Flag by the given value. It will be set if the signed input value is below zero, and cleared if it is zero or positive.

Stack Access

Similar to the flag register functions, this is mostly for compatibility with M68K code.

Avoid using these, as there are usually better ways of temporarily saving values (namely using local variables) or passing values between functions.

`void push(u32 value)`

- Pushes the given value onto the stack.

`u32 pop()`

- Returns the topmost value from the stack and removes it there.

Memory Data Processing

`void copyMemory(u32 destAddress, u32 sourceAddress, u32 bytes)`

- Copies data from one address in memory (e.g. RAM or ROM) to another.

`void zeroMemory(u32 startAddress, u32 bytes)`

- Clears a part of memory by writing zeroes there.

`void fillMemory_u8(u32 startAddress, u32 bytes, u8 value)`

`void fillMemory_u16(u32 startAddress, u32 bytes, u16 value)`

`void fillMemory_u32(u32 startAddress, u32 bytes, u32 value)`

- Fills a part of memory by writing multiple copies of the given value there.

Persistent Data Access

Persistent data is stored in a file inside the user's data directory. It can be used for saving game progress, settings, etc.

The persistent data file internally is built up of multiple packages with arbitrary strings as identifying names / keys. This way, you can store multiple different types of data inside the same persistent data file.

u32 System.loadPersistentData(u32 targetAddress, u64 key, u32 maxBytes)

- Loads data from the persistent data file.
- Pass a string as key that identifies which persistent data package you want to load.
- Returns the number of bytes written to the target address, this can be 0 if no persistent data existed with the given key.

void System.savePersistentData(u32 sourceAddress, u64 key, u32 bytes)

- Saves data from memory into the persistent data file.
- Pass a string as key that identifies which persistent data package you want to overwrite. If the key is not used yet, a new package will be created.

u32 SRAM.load(u32 address, u16 offset, u16 bytes)

void SRAM.save(u32 address, u16 offset, u16 bytes)

- Deprecated. (This was part of the old SRAM-emulating system that got used before the more flexible persistent data functions were a thing.)

Raw Data Loading

bool System.hasExternalRawData(u64 key)

- Returns true if there is a raw data file registered under the given key.
- The key must be a string.

u32 System.loadExternalRawData(u64 key, u32 targetAddress)

- Loads data from a raw data file into memory.
- Returns the number of bytes loaded. This can be zero if no raw data was registered under the given key.

u32 System.loadExternalRawData(u64 key, u32 targetAddress, u32 offset, u32 maxBytes, bool loadOriginalData, bool loadModdedData)

- Same as above, but with more parameters.
- Parameters offset and maxBytes determine which part of the raw data to load. You can set maxBytes to zero to load everything starting at offset.
- Parameters loadOriginalData and loadModdedData can limit raw data loading to keys defined as part of the game itself or a mod for that game, respectively.

bool System.hasExternalPaletteData(u64 key, u8 line)

- Returns true if there is a custom palette defined in the game's or mod's palettes data directory with the given key.
- Use the palette's file name (without extension .png) as key.

u16 System.loadExternalPaletteData(u64 key, u8 line, u32 targetAddress, u8 maxColors)

- Loads data from a custom palette defined in the game's or mod's palettes data directory.
- Returns the number of colors loaded.
- Colors will get loaded in 32-bit ABGR format, i.e. with one byte per channel, and red in the least significant byte.

Game Resolution

u16 getScreenWidth()

- Returns the width in pixels of the simulated game screen.

u16 getScreenHeight()

- Returns the height in pixels of the simulated game screen.

u16 getScreenExtend()

- Returns the additional pixels on each side of the screen for widescreen display.

- This is calculated as:
`(getScreenWidth() - 320) / 2`

Input

`u8 buttonDown(u8 index)`

- Returns true if the button with the given index is held down at the moment.
- Index ranges from 0x00 to 0x0f for player 1's input. Add 0x10 to query player 2's input instead.

`u8 buttonPressed(u8 index)`

- Returns true if the button with the given index was just pressed this frame, i.e. is now held down but wasn't before.

Miscellaneous

`u32 System.rand()`

- Returns a random u32 number.
- Usage of this function breaks determinism of scripts, which can make debugging much harder. E.g. game recordings including a call to „System.rand“ won't work properly and input recordings won't produce the same results each time.
- For that reason, if you need random number, better rely on a script-implemented pseudo-random number generator.

Debugging

`Log = ...`

- Not a function actually, but some kind of global variable. Though it can only be written to.
- This is a quick way of logging an integer value (up to 32-bit) onto the screen.

- Usage example: `Log = D0.u16`
- Note that one one logged value per script line that uses Log will stay visible on the screen. So when using this, you might want to step frame by frame, or run until a logging occurs.

`void debugLog(u64 stringHash)`

- Writes the string to the debug log.
- This is the more sophisticated version of the Log variable, this time as an actual function.

`void debugLogColors(u64 name, u32 startAddress, u8 numColors)`

- Outputs multiple colors as palette debug box on the screen.
- It will only be visible for a single frame, so you might want to step frame by frame, or run until a logging occurs.

`void System.writeDisplayLine(u64 stringHash)`

- Writes text into the display line at the bottom of the screen.
- The parameter must be a string.
- Text written to the display line will stay there briefly before fading out.

`void scriptAssert(bool condition)`

- Triggers an error message box if the condition is false.

`void debugWatch(u32 ramAddress, u16 bytes)`

- Adds a debug watch on the given address in RAM or shared memory.

`void debugDumpToFile(u64 filename, u32 startAddress, u32 bytes)`

- Save parts of memory to a file. The filename parameter must be a string.
- The file will be created in the game's working directory, which is usually the executable directory.

Control Flow

`void yieldExecution()`

- Signals the end of the current frame. The script will continue after this call in the next frame.
- Best practise: Call this only in a single script function that acts as a general function ending a frame. When modding a game, you usually wouldn't use this at all.

`void System.setupCallFrame(u64 functionName)`

- Creates a new entry on the call stack, at the start of the given script function.
- The parameter must be a string, the name of the script function to use. This only works for functions without parameters and return values.

`void System.setupCallFrame(u64 functionName, u64 labelName)`

- Creates a new entry on the call stack, at a label inside the given script function.
- The parameters must both be a strings, the function name (see above), and the name of the label.

Direct VRAM Access

`u16 getVRAM(u16 vramAddress)`

- Reads a u16 value (2 bytes) from the given VRAM address.

`void setVRAM(u16 vramAddress, u16 value)`

- Writes a u16 value (2 bytes) to the given VRAM address.

Emulated VDP (Video Display Processor)

`void VDP.setupVRAMWrite(u16 vramAddress)`

- Set the VRAM address to use for subsequent calls to `VDP.readData*` and `VDP.writeData*`.

`void VDP.setupVSRAMWrite(u16 vsramAddress)`

- Set the address in VSRAM (vertical scroll offsets) to use for subsequent calls to `VDP.readData*` and `VDP.writeData*`.

`void VDP.setupCRAMWrite(u16 cramAddress)`

- Set the address in CRAM (colors) to use for subsequent calls to `VDP.readData*` and `VDP.writeData*`.

`void VDP.setWriteIncrement(u16 increment)`

- Set the number of bytes to advance after each call to `VDP.readData16` and `VDP.writeData16`.

`u16 VDP.readData16()`

- Read a u16 (i.e. 2 bytes) from VRAM / VSRAM / CRAM at the address previously defined with one of the calls above.
- The address will be increased by the current write increment in each call, so multiple calls to this function read from different addresses each time.

`u32 VDP.readData32()`

- Same as `VDP.readData16`, but reads a u32 (i.e. 4 bytes).
- Note that internally, this is two calls to `VDP.readData16`, so write increment is applied once in between and once afterwards.

`void VDP.writeData16(u16 value)`

- Write a u16 value to VRAM / VSRAM / CRAM. See `VDP.readData16` for more information.

`void VDP.writeData32(u32 value)`

- Write a u32 value to VRAM / VSRAM / CRAM. See `VDP.readData32` for more information.

`void VDP.copyToVRAM(u32 address, u16 bytes)`

- Copy memory from the given address (in RAM, extended RAM, or ROM) into VRAM / CRAM / VSRAM.
- This acts like several subsequent calls to `VDP.writeData16`, so uses the previously defined VRAM / CRAM / VSRAM address.

`void VDP.zeroVRAM(u16 bytes)`

- Fill parts of VRAM with zeroes.
- This acts like several subsequent calls to `VDP.writeData16`, so uses the previously defined VRAM / CRAM / VSRAM address.

`void VDP.fillVRAMbyDMA(u16 fillValue, u16 vramAddress, u16 bytes)`

- Fill parts of VRAM with the given u16 value.

`void VDP.copyToVRAMbyDMA(u32 sourceAddress, u16 vramAddress, u16 bytes)`

- Copy memory from the given address (in RAM, extended RAM, or ROM) into VRAM.
- This is a more handy version of the `VDP.setupVRAMWrite` + `VDP.copyToVRAM` combination.

`void VDP.copyToCRAMbyDMA(u32 sourceAddress, u16 vramAddress, u16 bytes)`

- Copy memory from the given address (in RAM, extended RAM, or ROM) into CRAM.
- This is a more handy version of the `VDP.setupVRAMWrite` + `VDP.copyToCRAM` combination.

`void VDP.Config.setActiveDisplay(u8 enable)`

- Enables or disables rendering.
- Only a blank screen in the backdrop color (black by default) will be shown while rendering is disabled.

`void VDP.Config.setNameTableBasePlaneB(u16 vramAddress)`

- Define the plane B name table base in VRAM.

`void VDP.Config.setNameTableBasePlaneA(u16 vramAddress)`

- Define the plane A name table base in VRAM.

`void VDP.Config.setNameTableBasePlaneW(u16 vramAddress)`

- Define the plane W name table base in VRAM.

`void VDP.Config.setVerticalScrolling(bool verticalScrolling, u8 horizontalScrollMask)`

- Enable or disable vertical scroll mode, i.e. usage of multiple scroll offsets in vertical direction stored in VSRAM.
- Also defines the scroll mask for horizontal scroll offsets. Common values are 0x00 (i.e. there's only one horizontal scroll value shared for all pixel lines), 0x07, 0xf8, and 0xff (i.e. there's a horizontal scroll value for each pixel line individually).

`void VDP.Config.setBackdropColor(u8 paletteIndex)`

- Sets the palette index to be used as backdrop color.

`void VDP.Config.setRenderingModeConfiguration(u8 shadowHighlightPalette)`

- Switches to other rendering modes. Not yet supported!

`void VDP.Config.setPlayfieldSizeInPixels(u16 width, u16 height)`

- Defines the size in pixels of plane A and plane B.
- Use only powers of two, between 256 and 1024 pixels for width and height.

`void VDP.Config.setPlayfieldSizeInPatterns(u16 width, u16 height)`

- Same as `VDP.Config.setPlayfieldSizeInPatterns`, but using patterns as input, with one pattern being 8 pixels in size.
- Valid values are powers of two, between 32 and 128 patterns for width and height.

`void VDP.Config.setupWindowPlane(bool useWindowPlane, u16 splitY)`

- Setup usage of plane W.
- If plane W is enabled, the screen will get split horizontally at pixel position `splitY`, with plane W being shown above and plane A shown below.

`void VDP.Config.setPlaneWScrollOffset(u16 x, u8 y)`

- Set plane W scroll offset.

Oxyger Renderer

`void Renderer.setPaletteEntry(u8 index, u32 color)`

- Set a palette entry directly without using the usual VDP mechanisms (involving CRAM).
- This way, you can access all entries up to index `0xff` and write a 32-bit color value in ABGR format (i.e. least significant byte is red). Note that the alpha channel will get ignored.
- This function needs to be called in each frame again, otherwise will only have an effect for a single frame.

`void Renderer.setPaletteEntryPacked(u8 index, u16 color)`

- Same as `Renderer.setPaletteEntry`, but using the packed 16-bit color format.
- Depending on its topmost bit, a color value can be one of the following:
 - the 9-bit VDP colors format 0000 BBB0 GGG0 RRR0
 - or an extended 15-bit format 1BBB BBGG GGGR RRRR

`void Renderer.enableSecondaryPalette(u8 line)`

- Enables a secondary palette to be used below the given pixel line.
- This is used e.g. in Sonic game projects for the split between normal and underwater colors.
- This function needs to be called in each frame again, otherwise will only have an effect for a single frame.

`void Renderer.setSecondaryPaletteEntryPacked(u8 index, u16 color)`

- Same as `Renderer.setPaletteEntryPacked`, but for the secondary palette.

`void Renderer.setScrollOffsetH(u8 setIndex, u16 lineNumber, u16 value)`

- Sets a horizontal scroll offset directly without using the usual VDP mechanisms.
- This allows you to access the usual plane A (`setIndex == 1`) and B (`setIndex == 0`) scroll offsets, but also additional scroll offset sets (indices 0x02 and 0x03) that can be useful for custom planes, see `Renderer.setupPlane`.
- This function needs to be called in each frame again, otherwise will only have an effect for a single frame.

`void Renderer.setScrollOffsetV(u8 setIndex, u16 rowNumber, u16 value)`

- Sets a vertical scroll offset directly without using the usual VDP mechanisms.
- See `Renderer.setScrollOffsetH` for more info.

`void Renderer.setHorizontalScrollNoRepeat(u8 setIndex, bool enable)`

- Enables or disables the "NoRepeat" mode for horizontal scrolling, for the given scroll offset set.
- If enabled, horizontal scrolling will not wrap back inside the plane, but fill everything outside with empty / transparent pixels.

`void Renderer.setVerticalScrollOffsetBias(s16 bias)`

- Set a bias value that the renderer will add to the screen x-position when determining which vertical scrolling offset should be used.
- Only used in vertical scroll mode.

`void Renderer.enforceClearScreen(bool enable)`

- If enabled, the screen will get completely cleared each frame.
- This is usually not enabled, as rendering of plane B will overwrite the whole screen anyway. But when using custom planes, it can make sense to enable this.

`void Renderer.enableDefaultPlane(u8 planeIndex, bool enabled)`

- Planes A and B will get rendered by default, but you can prevent that with this function. Useful if you have custom planes as a replacement, see `Renderer.setupPlane`.

`void Renderer.setupPlane(s16 px, s16 py, s16 width, s16 height, u8 planeIndex, u8 scrollOffsets, u16 renderQueue)`

- Define a custom plane for a particular rectangle on the screen.
- Parameters:
 - px, py, width, height define the rectangle on screen
 - planeIndex refers to: 0x00 = plane B non-prio layer, 0x01 = plane A non-prio layer, 0x02 and 0x03 = plane B / A priority layers

- scrollOffsets is the index of one of the scroll offset set to use, usually 0x00 (plane B offsets) or 0x01 (plane A offsets), but can as well be a custom set (0x02 and 0x03)
- renderQueue defines when this plane will get rendered in relation to other planes and sprites
- This function mainly exists to allow for more obscure things like e.g. rendering plane A with different scroll offsets on the upper and lower parts of the screen.

`void Renderer.resetCustomPlaneConfigurations()`

- Removed previously defined custom planes and restores the default planes again.

`void Renderer.resetSprites()`

- Clears the list of sprites to be rendered.
- This is meant to be done once per frame before starting to draw sprites again. However, there might be situations where the last sprites shown should just remain, like just fading out the last image – in this situation, do not call this function and do not draw any new sprites.

`void Renderer.drawVdpSprite(s16 px, s16 py, u8 encodedSize, u16 patternIndex, u16 renderQueue)`

- Draws a sprite like the VDP does on original Mega Drive / Genesis hardware (VDP using its data in the sprite attributes table = SAT).
- Parameters:
 - px and py is the position on screen. Note that this is using actual screen coordinates (without the 0x80 offset preset in the SAT)
 - encodedSize is a byte of the format 00WW00HH, where WW is the width and HH is the height between 00 (1 pattern = 8 pixels) and 11 (4 patterns = 32 pixels)
 - patternIndex is an encoded reference to the patterns to use for drawing; same format as in SAT
 - renderQueue defines when this sprite will get rendered in relation to other sprites and the planes

`void Renderer.drawVdpSpriteWithAlpha(s16 px, s16 py, u8 encodedSize, u16 patternIndex, u16 renderQueue, u8 alpha)`

- Same as `Renderer.drawVdpSprite`, but supporting an additional alpha transparency value (0xff for full opacity).

`void Renderer.drawVdpSpriteWithTint(s16 px, s16 py, u8 encodedSize, u16 patternIndex, u16 renderQueue, u32 tintColor, u32 addedColor)`

- Same as `Renderer.drawVdpSprite`, but supporting a multiplicative tint color and an additive color, both in ABGR format.

`bool Renderer.hasCustomSprite(u64 key)`

- Check if there is a custom / modded sprite with the given key. The key must be a string here.

`void Renderer.drawCustomSprite(u64 key, s16 px, s16 py, u8 atex, u8 flags, u16 renderQueue)`

`void Renderer.drawCustomSprite(u64 key, s16 px, s16 py, u8 atex, u8 flags, u16 renderQueue, u8 angle, u8 alpha)`

`void Renderer.drawCustomSprite(u64 key, s16 px, s16 py, u8 atex, u8 flags, u16 renderQueue, u8 angle, u32 tint, s32 scale)`

- Draw a custom / modded sprite.
- Parameters:
 - key is a string referencing a custom sprite loaded from a PNG or BMP file, or it's the result of a `Renderer.setupCustom*Sprite` call
 - px and py denote the position where to draw the sprite on the screen
 - atex is an offset added to palette indices inside palette sprites (not used for component sprites loaded from PNGs)
 - flags is a combination of:
 - 0x01 = flip horizontally
 - 0x02 = flip vertically
 - 0x20 = interpret px/py as world space coordinates (see `setWorldSpaceOffset`) instead of a screen position
 - 0x40 = draw sprite with priority flag
 - 0x80 = ignore global tint and added color, even if this is an component sprite, where those would usually be applied automatically

u64 Renderer.setupCustomUncompressedSprite(u32 sourceBase, u16 words, u32 mappingOffset, u8 animationSprite, u8 atex)
u64 Renderer.setupCustomCharacterSprite(u32 sourceBase, u32 tableAddress, u32 mappingOffset, u8 animationSprite, u8 atex)
u64 Renderer.setupCustomObjectSprite(u32 sourceBase, u32 tableAddress, u32 mappingOffset, u8 animationSprite, u8 atex)
u64 Renderer.setupKosinskiCompressedSprite(u32 sourceAddress, u32 mappingOffset, u8 animationSprite, u8 atex)

- Creates a custom sprite from the ROM or RAM.
- These functions are somewhat game-specific, see the existing scripts for examples.

void Renderer.addSpriteMask(s16 px, s16 py, s16 width, s16 height, u16 renderQueue, u8 priorityFlag)

- Add a mask that hides all sprites with a lower render queue.

void Renderer.addSpriteMaskWorld(s16 px, s16 py, s16 width, s16 height, u16 renderQueue, u8 priorityFlag)

- Same as `Renderer.addSpriteMask`, but uses world space coordinates.

void Renderer.resetViewport(u16 renderQueue)

- Reset a previous reduction of the viewport to a smaller portion of the screen, see `Renderer.setViewport`.

void Renderer.setViewport(s16 px, s16 py, s16 width, s16 height, u16 renderQueue)

- Reduce the viewport to a smaller portion of the screen.

void Renderer.setGlobalComponentTint(s16 tintR, s16 tintG, s16 tintB, s16 addedR, s16 addedG, s16 addedB)

- Define the global tint color and added color, which will get applied to component sprites.
- For tintR/G/B, a value of 0x100 would be a neutral value that does not introduce any change to the colors.

- For addedR/G/B, these are values to be added to the respective 8-bit pixel channel value, after applying tint. You can make use of negative values here as well, to darken component sprites on the screen.

Audio Playback

`void Audio.playAudio(u64 sfxId)`

- Starts playback of a sound effect or music track.
- The parameter can be a string referring to a sound ID as defined in "audio_replacement.json" (e.g. "1F_sonic3"), or a u8 value that will be mapped automatically to the respective hex code string (e.g. 0x1c will be interpreted as the string "1C").
- Some sound IDs use a defined channel, which means it can only be played once at a time. Starting a new sound of a channel will stop playback of other sounds using the same channel.

`bool Audio.isPlayingAudio(u64 sfxId)`

- Checks if a sound effect or music track with the given sound ID is already playing.

`void Audio.stopChannel(u8 channel)`

- Stops the sound / music using the given channel.
- Can be used to e.g. stop the music, which is usually taking channel 0.

`void Audio.fadeOutChannel(u8 channel, u16 length)`

- Fades out and afterwards stops the sound / music using the given channel.
- The length parameter is expressed in 1/256 seconds, so a value of 0x280 would refer to 2.5 seconds of fade-out time.

`void Audio.fadeInChannel(u8 channel, u16 length)`

- Fades in the sound / music using the given channel. This only really makes sense for sounds / music that are right in the middle of fading out.

`void Audio.pushBackChannel(u8 channel)`

- Pauses playback of the given channel, so that a different sound / music using the same channel can be started. When its playback stops, the old sound / music will fade in and continue.
- A use-case for this would be the extra life jingle in Sonic games, which are meant to pause but not stop the main music, and let it continue as soon as the jingle finished playing.

`void Audio.enableAudioModifier(u8 channel, u8 context, u64 postfix, u32 relativeSpeed)`

`void Audio.disableAudioModifier(u8 channel, u8 context)`

- These are highly specialized functions only added to handle sped-up versions of music tracks in S3&K. See usage there for examples.

Misc Functions

`void setWorldSpaceOffset(s32 px, s32 py)`

- Set the position of the upper left corner of the screen inside the world space coordinate system.
- This makes sense to set in 2D scrolling games to be able to use world space coordinates instead of screen space coordinates e.g. when drawing custom sprites.

`void debugDrawRect(s32 px, s32 py, s32 sx, s32 sy)`

`void debugDrawRect(s32 px, s32 py, s32 sx, s32 sy, u32 color)`

- Draw a rectangle on the screen for debugging purposes.

- Uses world space coordinates.

Undocumented

The following functions exist and can be used, but there's no documentation aside from the signature. But you can search for their usage in scripts to get an idea what for and how they are used.

```
bool ROMDataAnalyser.hasEntry(u64 categoryHash, u32 address)
void ROMDataAnalyser.beginEntry(u64 categoryHash, u32 address)
void ROMDataAnalyser.endEntry()
void ROMDataAnalyser.addKeyValue(u64 keyHash, u64 valueHash)
void ROMDataAnalyser.beginObject(u64 keyHash)
void ROMDataAnalyser.endObject()

bool System.SidePanel.setupCustomCategory(u64 shortName, u64 fullName)
bool System.SidePanel.addOption(u64 stringHash, bool defaultValue)
void System.SidePanel.addEntry(u64 key)
void System.SidePanel.addLine(u64 stringHash, s8 indent)
void System.SidePanel.addLine(u64 stringHash, s8 indent, u32 color)
bool System.SidePanel.isEntryHovered(u64 key)
```

RENDERING

Render Queues Overview

Most script functions meant for rendering something on the screen – e.g. sprites and planes – have a render queue parameter.

This is used to determine the order of rendering independent of the order of script calls.

Render queues in theory range from 0x0000 to 0xffff, with lower values getting rendered first, and higher values overwriting them. In other words, if you want to render something in front of everything else, use a high render queue like 0xf000.

Common render queue values:

- 0x1000 for plane B non-prio layer
- 0x1800 is where background blur gets applied to everything in lower render queues
- 0x2000 for plane A / W non-prio layer
- 0x3000 for plane B priority layer
- 0x4000 for plane A / W priority layer
- 0x9000 .. 0xa000 for game object sprites
- 0xe000 for UI elements

Palette vs. Component Sprites

Palette sprites

- This term covers all custom sprites loaded from 8-bit BMPs, plus those created from game data (see `Renderer.setupCustom*Sprite` script functions).
- Palette sprites are internally stored as one 8-bit index per pixel, i.e. as indexed image. They won't work without a palette.

Component sprites

- These are loaded from 32-bit PNGs.
- Component sprites are internally stored in 32-bit ABGR format, i.e. with 8 bits per red, green and blue channel and an 8-bit alpha channel that usually will get alpha blended when being rendered.
- The game automatically applies a global tint color and an added color when rendering a component sprites. This is used for effects like fading from / to a black or white screen. This behavior can be disabled in the draw script call, see `Renderer.drawCustomSprite`.